



Configuring Azureus with HTTP-tunnel



[HTTP-Tunnel.com Forum Index -> Documentation](#)

[View previous topic](#) :: [View next topic](#)

Author	Message
<p>luixo Official Beta Tester</p> <p>Joined: 07 Jul 2005 Posts: 11 Location: México</p>	<p> Posted: Wed Jul 13, 2005 5:32 am Post subject: Configuring Azureus with HTTP-tunnel </p> <hr/> <p>Ray asked me how to configure Azureus to work with http-tunnel, so I explain how below:</p> <p>When you have started HTTP-Tunnel, open Azureus, go to Tools -> Options (or use ctrl + ,).</p> <p>Now you are in the options window, first you need to determine an open port, in my case the port is 6900 the only port my ISP has open - if your ISP doesnt have any port open, dont worry.</p> <p>Next you need to determine the max number of simultaneous outbounds connections that you want to have, remember if you have SP2 the system limit its 10, you need to aply a patch to change this value (from http://www.lvllord.de/)</p> <p>In proxy options you can enable the first option "Enable proxying of tracker communications" (this option its for communicating with the tracker), be aware if you use a registered tracker its better to not check this option. If you enable this option use the following:</p> <p>Host: 127.0.0.1 Port: 1080</p> <p>Next option "Enable proxying of peers communication" (this option is for connecting to other clients). In the socks option i use V5, because i know it supports UDP. If you have checked "Enable proxying of tracker communications" then you can use the same proxy settings for trackers and peer communications, if</p>

not, enter the following :

Host: 127.0.0.1

Port: 1080

Restart azureus and enjoy.




Edit: -

Thanks for the guide!

-bluethought, HTTP-Tunnel Corp.

[Back to top](#)



bluethought

Site Admin

Joined: 25 Jun 2005

Posts: 2113

Posted: Wed Jul 13, 2005 8:24 pm Post subject:



The patch for Sp2 is available at <http://www.lvllord.de/> A good limit to use is 50-100.

[Back to top](#)



Display posts from previous:



[HTTP-Tunnel.com Forum Index](#) -> [Documentation](#)

All times are GMT

Page 1 of 1

Jump to:

You **can** post new topics in this forum

You **can** reply to topics in this forum

You **cannot** edit your posts in this forum

You **cannot** delete your posts in this forum

You **cannot** vote in polls in this forum

Powered by [phpBB](#) © 2001, 2005 phpBB Group